
Title: Installing the USB Sentinel Driver on Windows XP

Gerber FastFact #: 3546

Supplied By: Software Test

Last Modified: December 13, 2001

Summary: You can change the OMEGA digitizing beep sounds.

Connect the USB block to the PC

Click on:

- Start
- Select Control Panel
- Select Add Hardware
- Click Next
- Select "Yes I have already connected the hardware"
- Click Next
- Select USB token
- Click Next
- "Point" it to the OMEGA1.54 (dated Dec. 28, 2000) CD-ROM
- Select Rainbow 5_3_7 folder
- Select Win NT folder
- Select I386 folder
- Select sntnlusb.sys

You will get the message "The software you are installing for this hardware: Rainbow Security Device has not passed Windows logo testing to verify its compatibility with Win XP."

Click on "Continue anyway"

You will get the message:

Completing the found new hardware wizard
Rainbow security device.

Click finish

Click finish